

GUIDE

erwin Data Intelligence

Reference Data Management Guide
15.0



Legal Notices

This Documentation, which includes embedded help systems and electronically distributed materials (hereinafter referred to as the Documentation), is for your informational purposes only and is subject to change or withdrawal by Quest Software, Inc and/or its affiliates at any time. This Documentation is proprietary information of Quest Software, Inc and/or its affiliates and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of Quest Software, Inc and/or its affiliates

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all Quest Software, Inc and/or its affiliates copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to Quest Software, Inc and/or its affiliates that all copies and partial copies of the Documentation have been returned to Quest Software, Inc and/or its affiliates or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, QUEST SOFTWARE, INC. PROVIDES THIS DOCUMENTATION AS IS WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL QUEST SOFTWARE, INC. BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF QUEST SOFTWARE, INC. IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is Quest Software, Inc and/or its affiliates Provided with Restricted Rights. Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © Quest Software, Inc. and/or its affiliates All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Contact erwin

Understanding your Support

Review [support maintenance programs and offerings](#).

Registering for Support

Access the [erwin support](#) site and click Sign in to register for product support.

Accessing Technical Support

For your convenience, erwin provides easy access to "One Stop" support for [erwin Data Intelligence \(erwin DI\)](#), and includes the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- erwin Support policies and guidelines
- Other helpful resources appropriate for your product

For information about other erwin products, visit <http://erwin.com/>.

Provide Feedback

If you have comments or questions, or feedback about erwin product documentation, you can send a message to distechpubs@erwin.com.

News and Events

Visit [News and Events](#) to get up-to-date news, announcements, and events. View video demos and read up on customer success stories and articles by industry experts.

Contents

Reference Data and Codeset Manager	7
Reference Data Manager	8
Creating Reference Folders	10
Managing Reference Folders	12
Creating Reference Tables	14
Importing Data from Spreadsheets	16
Adding Columns to Reference Tables	19
Adding Column Values Manually	22
Importing Column Values from MS Excel Files	24
Importing Column Values Through DB Scans	26
Managing Reference Tables	30
Creating Publish Environments	32
Adding Validation Rules	33
Associating Validation Rules with Reference Tables	36
Running Validations Against Reference Tables	38
Associating Codesets With Reference Tables	40
Versioning Reference Tables	42
Publishing Reference Tables	45
Associating Reference Tables with Mappings	49
Codeset Manager	51
Maintaining Enterprise Codesets	53
Creating Categories	54

Managing Categories	56
Assigning Users	58
Adding Codesets	60
Entering Codes Manually	62
Importing Codes using MS Excel Files	66
Importing Codes into Code Value Grid using DB Scan	68
Managing Codesets	73
Versioning Codesets	76
Deleting Codes and Codesets	79
Publishing Codesets	82
Maintaining Code Mappings	86
Creating Categories	87
Managing Categories	90
Creating Code Crosswalks (Mappings)	92
Creating Code Crosswalks - Source and Target Codesets with Same Code Value	92
Creating Code Crosswalks - Source and Target Codesets with Different Code Value	94
Editing Code Mappings	99
Versioning Code Mappings	102
Associating Code Maps with Data Item Mappings	104
Publishing Code Maps	104
Associating Code Maps	106

Reference Data and Codeset Manager

This section walks you through reference data and codeset management.

- Reference data management is done via Reference Data Manager. It involves creating database like structures to maintain all your reference data. You can add reference data in a reference table from a spreadsheet, manually or via a DB scan. To validate reference tables for data quality tests, you can use SQL queries. You can also version, publish (to environments like production, development, test etc.), and link the reference tables to relevant mappings.

For further information on accessing and using the Reference Data Manager, refer to the [Reference Data Manager](#) topic.

- Codeset management is done via Codeset Manager. It involves creating, managing, and mapping codesets in the Codeset Manager. It has two sections:
 - Enterprise Codesets:** Under the Enterprise Codesets section, you can create and manage codesets. It involves importing legacy codesets, categorizing codesets, defining code values, versioning codesets, and publishing codesets to various environments.
 - Codeset Mappings:** Under the Codeset Mappings section, you can create and manage code crosswalks (mappings). It involves categorizing code mappings, defining code crosswalks, versioning code crosswalks, and publishing code crosswalks to various environments.

For further information on accessing and using the Codeset Manager, refer to the [Codeset Manager](#) topic.

Reference Data Manager

To access the Reference Data Manager, go to **Application Menu > Data Catalog > Reference Data Manager**. The Reference Data Manager dashboard appears:

The screenshot shows the Reference Data Manager interface with four numbered sections:

- 1-Workspace:** A sidebar on the left containing a tree view of the workspace hierarchy: Reference Datasets, Audit History, Validation Rules (highlighted), Environments, Reference Folders, EDW, EON, Erwin, Erwin_Sales, NASDAQ HEALTHCARE, and New_Folder.
- 2-Validation Rule Grid:** A table displaying validation rules. The table has columns: #, Validation Name, Validation Description, Created By, Created Date, Modified By, Modified Date, Validation Rule, Edit, and Delete. It contains four rows of data.
- 3-Additional Table Information:** A pane at the bottom right, currently empty.
- 4-Published Tables:** A pane at the bottom left, currently empty.

UI Section	Function
1-Workspace	Use this pane to browse and work on validation rules, environments, reference folders, and reference tables.
2-Right Pane	Use this pane to work on the data based on your selection in the Workspace pane.
3-Additional Table Information	Use this pane to view or work on additional information of a reference table selected in the Workspace pane.
4-Published Tables	Use this pane to browse, view, and export published reference tables.

Managing reference data involves the following:

- [Creating reference folders](#)
- [Creating reference tables](#)
- [Creating publish environments](#)
- [Adding validation rules](#)
- [Associating codesets with reference tables](#)
- [Versioning reference tables](#)


- [Associating reference tables with mappings](#)

Creating Reference Folders

Reference folders group reference tables based on your data integration project. Therefore, before creating reference tables, you need to create a reference folder. You can also create sub-folders to group reference tables further.

To create reference folders, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, right-click the **Reference Folders** node.



3. Click **New Folder**.

The New Folder page appears.

The screenshot shows the 'New Folder' dialog box. It has a title bar with a folder icon and the text 'New Folder'. Below the title bar, there are two input fields: 'Folder Name*' with a text box and 'Folder Description:' with a larger text area. There are also icons for a folder and a close button (X) in the top right corner.

4. Enter the **Folder Name** and **Folder Description**.

For example:

- **Folder Name:** City Names
- **Folder Description:** This folder contains reference tables for city names.

or click .

The folder is created and saved in the Reference Folders tree.

Once a reference folder is created, you can manage it using the options available on right-clicking the reference folder. [Managing reference folders](#) involves:

- Creating sub-folders
- Editing reference folders
- Assigning users
- Deleting reference folders


Managing Reference Folders

Managing reference folders involves:

- Creating sub-folders
- Editing reference folders
- Assigning users
- Deleting reference folders

To manage reference folders, follow these steps:

1. In the **Workspace** pane, right-click a reference folder.



2. Use the following options:

New Sub Folder

Edit Folder

Use this option to update reference folder's name and description.

Assign Users

Use this option to assign users to a reference folder based on project, departments, functions, and so on. On the Assign Users page, select user IDs under **User ID** list-box and move them to **Assigned Users** list-box using the arrows ( or ). Similarly, to change existing user assignment, select user IDs under **Assigned Users** list-box and move them back to **User ID** list-box using the arrows ( or ).

Delete

Use this option to delete a reference folder that is no more required.


Creating Reference Tables

Reference tables store reference data. You can create reference tables in new or existing reference folders. You can also create reference tables under the reference sub-folders.

To create reference tables, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, right-click a reference folder or sub-folder.

For example, if you right-click a reference folder the following options appear.



3. Click **New Table**.

The New Reference Table page appears.

Creating Reference Tables

Save
Cancel

Folder Name :

Table Name* :

Version :

Owner* :

Data Steward : -Select Data Steward- ▼

Description :

Import Data from Spreadsheet ☐

+
×

Column Name	Order

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Folder Name	Specifies the name of the reference folder. For example, NASDAQ Healthcare. It is autopopulated and cannot be edited.
Table Name	Specifies the name of the reference table. For example, Data_Classifications_Levels.
Version	Specifies the version of the reference table. For example, 1.00. It is autopopulated and cannot be edited.
Owner	Specifies the reference table owner's name. For example, Talon Smith.

Creating Reference Tables	
Field Name	Description
Data Steward	Specifies the name of the data steward responsible for the reference table. For example, Jane Doe. Users assigned with the Legacy Data Steward role appear as drop down options. You can assign this role to a user in the Resource Manager. To assign data steward, select a data steward from the drop down options.
Description	Specifies the description about the reference table. For example: This reference table serves as domain for the data classification column.
Import Data from Spreadsheet	Use this check box to import reference data into the reference table from the XLSX file. For more information, refer to the Importing Data from Spreadsheets section below.

5. Click .

A reference table is created and saved in the Reference Tables tree.

Importing Data from Spreadsheets

To import reference data from MS Excel files, follow these steps:

1. On the **New Reference Table** page, click the **Import Data from Spreadsheet** check box.

Creating Reference Tables

Next

Cancel

Folder Name :

erwin Sales

Table Name* :

HR_REF_TABLE

Version :

1.00

Owner* :

Sojha

Data Steward :

John Doe

Description :

This is a reference table for HR Dept.

Import Data from Spreadsheet

☒

Drag-n-Drop files here or
click to select files for upload.



- Drag and drop or use  to browse and select the XLSX file.
- Click **Next**.

The Preview Screen page appears. To exclude a column from the import process, double-click the column header and click **NOT_IN_USE**.

Preview Screen

Table Name: HR_REF_TABLE

To exclude a column from the import process, double click on the column header and select 'NOT_IN_USE'

S.NO	TABLE_NAME	TABLE_DEF	TABLE_COMMENTS	LOGICAL_TABLE_NAME	COLUMN_NAME	COL_DEF
1	dbo.RM_RESOURCE_New				RESOURCEID_New	
2	dbo.RM_RESOURCE_New				RESOURCENAME_New	
3	dbo.RM_RESOURCE_New				RESOURCEDESC_New	
4	dbo.RM_RESOURCE_New				RESOURCECELLPHONE_Ne	
5	dbo.RM_RESOURCE_New				RESOURCEHOMEPHONE_N	
6	dbo.RM_RESOURCE_New				RESOURCEEMAIL_New	

- Click .

The reference data is imported into the reference table.

If you do not click the Import Data from Spreadsheet check box, you need to [add columns](#) to the reference table and then add column values:

- [From MS Excel files](#)
- [Through DB scans](#)

You can manage a reference table using the options available on right-clicking the reference table. [Managing reference tables](#) involves:


- Altering reference tables
- Copying reference tables
- Assigning users to reference tables
- Deleting reference tables

Adding Columns to Reference Tables

After creating a reference table, you can add columns to the reference table.

To add columns to reference tables, follow these steps:

1. In the **Workspace** pane, right-click a reference table.



2. Click **Alter Table**.

The Alter Table page appears.

Adding Columns to Reference Tables

Folder Name :

Erwin

Table Name* :

T_NAME

Version :

1.00

Owner* :

Samuel

Data Steward :

janedoe

Description :

Reference Table for data integration project.

Created By :

Administrator

Created Date :

2019-12-23 17:13:09.15

Modified By :

Modified Date :

Column Name	Order	Created By	Created Date	Modified By	Modified Date

3. Click .

A new row is added to the grid.

4. Double-click the cell under the **Column Name** and enter the column name.
You can add multiple columns.




Folder Name :

Table Name* :

Version :

Owner* :

Data Steward :

Description :

Created By : Created Date :

Modified By : Modified Date :




Column Name	Order	Created By	Created Date	Modified By	Modified Date
ID	1				
NaN					

5. Click .

The columns are added to the reference table.

Once columns are added to a reference table, you can import column values:

- Manually
- From MS Excel files
- Through DB scans


Adding Column Values Manually

You can add data to a reference table manually. It involves adding columns to the reference table and then adding column values. For more information on adding columns to reference tables, refer to the [Adding Columns to Reference Tables](#) topic.

To add column values manually, follow these steps:

1. In the **Workspace** pane, click a reference table.


Columns in the reference table appears.



2. Click .

3. Click .

The Add Reference Data page appears.



4. Double-click the cells under the columns and type the respective column values.

Adding Column Values Manually

ID	NAME
12341	
	Andrew

5. Click .

The column values are added to the reference table.


Importing Column Values from MS Excel Files

You can import reference data from MS Excel files into reference tables. First, you need to add columns to a reference table and then import column values from an MS Excel file. For more information on adding columns to reference tables, refer to the [Adding Columns to Reference Tables](#) topic.

To import column values from MS Excel files, follow these steps:

1. In the **Workspace** pane, click a reference table.

Columns in the reference table appear.



2. Click .
3. Click .

The Import Table Data page appears.




4. Click **Choose File** and browse and select the XLSX file.
5. Click .

The Import Table Data page appears.

6. Double-click the **Select Column to Import** cell of the required column.

Importing Column Values from MS Excel Files



ID	CREATED BY	CREATED DATE	MODIFIED BY	MODIFIED DATE
ID	Clear Selection	Select Column To Import	Select Column To Import	Select Column To Import
813	ID	2019-09-11 14:09:18.503	Administrator	2019-09-11 14:15:20.543
813	NAME	2019-09-11 14:09:18.503	Administrator	2019-09-11 14:15:20.543
813	Clear Selection	2019-09-11 14:09:18.503	Administrator	2019-09-11 14:15:20.543
813	Administrator	2019-09-11 14:09:18.503	Administrator	2019-09-11 14:15:20.543
813	Administrator	2019-09-11 14:09:18.503	Administrator	2019-09-11 14:15:20.543
813	Administrator	2019-09-11 14:09:18.503	Administrator	2019-09-11 14:15:20.543

7. Select the appropriate <Column_Name>.

You can select multiple columns.

8. Click .

The column values are imported from the XLSX file.


Importing Column Values Through DB Scans

You can import reference data from a database to a reference table by connecting the database to the application. It involves adding columns to reference table and then importing column values from the database. For more information on adding columns to reference tables, refer to the [Adding Columns to Reference Tables](#) topic.

To import column values from databases, follow these steps:

1. In the **Workspace** pane, click a reference table.

Columns in the reference table appear.



2. Click .
3. Click .

The DB Scan page appears.

Importing Column Values Through DB Scans

☐ Delete And Reload

Query Panel

Quick Connection

* Mandatory Fields

DBType: * Select DB Type

Driver Name:

IP Address/Host Name: *

Port: *

Database Name: *

User Name: *

Password: *

Preview

Note*: Only top 50 rows will be displayed in grid.

4. Enter appropriate values in the fields on the **Quick Connection** tab to establish a connection with a database. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
DB Type	Specifies the database type. For example, Sql Server.
Driver Name	Specifies the JDBC driver name for connecting to the database. For example, com.microsoft.sqlserver.jdbc.SQLServerDriver The field is autopopulated based on the DB Type.
IP Address/Host Name	Specifies the IP address or server host name of the database. For example, localhost.
Port	Specifies the port to connect with the database. For example: 1433 is the default port for a Sql Server database type.
Database Name	Specifies the database name being used to connect to the reference table. For example, ErwinDIS931.

Importing Column Values Through DB Scans

Field Name	Description
User Name	Specifies the user name to connect with the database. For example, sa.
Password	Specifies the password to connect with the database. For example, goerwin@1.

- Click  to test the connection.


If the connection is established, the success message appears.

- Write a query in the **Query Panel** to pull the data from the database.

- Click  to validate the query.

- Click  to preview the data.

The data is previewed.



The screenshot shows the DB Scan application interface. On the left, the 'Query Panel' contains a text area with the query 'select * from dbo.Project'. On the right, the 'Quick Connection' panel shows mandatory fields: DBType (Sql Server), Driver Name (com.microsoft.sqlserver.jdbc.SQL), IP Address/Host Name (localhost), Port (1433), Database Name (ErwinDIS931), User Name (sa), and Password (masked). Below these panels is a 'Preview' section displaying a table with 7 columns: SNo, PROJ_ID, PROJ_NAME, PROJ_DESCR, PROJ_COST_CENTER, PROJ_IT_SPONSOR_FULL_NAME, and PROJ_BUS_SPONSOR. The table contains 6 rows of data, with the first row showing 'Select column to import' for PROJ_ID, PROJ_NAME, PROJ_DESCR, PROJ_COST_CENTER, PROJ_IT_SPONSOR_FULL_NAME, and PROJ_BUS_SPONSOR.

- Double-click the **Select Column to Import** cell under the required column.

A drop-down option appears displaying the reference columns.

Importing Column Values Through DB Scans

SNO	PROJ_ID	PROJ_NAME	PROJ_DESCR	PROJ_COST_CENTER	PROJ_IT_SPONSOR_FULL_NAME	PROJ_BUS_SPONSOR
	ID	Select column to import	Select column to import	Select column to import	Select column to import	Select column to import
1	1	ID				
2	2	NAME				
3	3	Clear selection				
4	4	Select column to import				
5	5	BFSI Integration				
6	6	Data Lake Migration				

10. Choose an appropriate <Reference_Column_Name> from the drop-down.

You can import multiple columns from the database.

11. Click .

The column values from the database are imported into the selected reference columns.


Managing Reference Tables

Managing reference tables involves:

- Altering
- Copying
- Assigning users
- Deleting

To manage reference tables, follow these steps:

1. In the **Workspace** pane, right-click a reference table.



2. Use the following options:

Alter Table

Use this option to update a reference table. You can edit table name, owner, data steward, and add or remove columns.

Copy

table in a reference folder. To paste the reference table, right-click the reference folder and click **Paste**.

Assign Users

Use this option to assign users to reference tables. Before, you assign a user to a reference table, ensure that the user is assigned to the corresponding reference folder.

On the Assign Users page, select user IDs under **User ID** list-box and move them to **Assigned Users** list-box using the arrows ( or ). Similarly, to change existing user assignment, select user IDs under **Assigned Users** list-box and move them back to **User ID** list-box using the arrows ( or .

Delete


Use this option to delete a reference table that is no longer required.

Creating Publish Environments

You can publish reference tables to various environments like development, production, test etc. You can also specify the schema of the environment, for example, DBO.

To create publish environments, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, right-click the **Environments** node.



3. Click **New Environment**.

The New Environment page appears.

4. Enter the **Environment Name** and **Schema Name**.

For example:

- **Environment Name:** Production
- **Schema Name:** DBO

5. Click .

The publish environment is created and saved on the Publish Environments page.

Adding Validation Rules

You can define a validation rule in the form of SQL queries and use it to validate reference tables.

To add validation rules, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, click the **Validation Rules** node.

The Validation Rule Grid page appears.

Validation Rule Grid									
#	Validation Name	Validation Description	Created By	Created Date	Modified By	Modified Date	Validation Rule	Edit	Delete
1	EMPLOYEE MANAGER CHECK	Rule to check for valid manag	Administrator	2018-10-19 09:05:10,					
2	EMPLOYEE NAME RULE	checking for valid employee r	Administrator	2018-10-19 09:05:40,	Administrator	2019-03-13 22:43:50,			
3	Incorrect_Object_Id	desc	Administrator	2019-09-11 14:11:59,					
4	INVALID EMP RULE		Administrator	2018-10-19 09:05:57,					

3. Click .

The New Validation Rule page appears.

New Validation Rule

Validation Name * :

Validation Description :

Validation Rule * :

Note* : Validation query should be in the following format for successful execution

Select ROW_NUM, 'VALIDATION ERROR MESSAGE' from ...
 Or
 Select ROW_NUM, 'VALIDATION ERROR MESSAGE' ERROR_MSG from ...

ROW_NUM should always be the first column and the validation error message should be the second column (with or without the column alias).

Adding Validation Rules

datory. Refer to the following table for field descriptions.

Field Name	Description
Validation Name	Specifies the name of the validation rule. For example, Incorrect_Object_ID.
Validation Description	Specifies the description about the validation rule. For example: This validation rule validates the ERWIN_SALES reference table.
Validation Rule	Specifies the SQL query of the validation rule. For example: select * from ERWIN_SALES where ID = 1000000.

5. Click .

The validation rule is created and saved in the Validation Rule Grid.

Validation Rule Grid									
#	Validation Name	Validation Description	Created By	Created Date	Modified By	Modified Date	Validation Rule	Edit	Delete
1	EMPLOYEE MANAGER CHECK	Rule to check for valid manager	Administrator	2018-10-19 09:05:10.51					
2	EMPLOYEE NAME RULE	checking for valid employee name	Administrator	2018-10-19 09:05:40.04	Administrator	2019-03-13 22:43:50.60			
3	Incorrect_Object_Id	desc	Administrator	2019-09-11 14:11:59.4					
4	INVALID EMP RULE		Administrator	2018-10-19 09:05:57.25					

Use the following options to work on the Validation Rule Grid page:

Validation Rule 

Use this option to view validation rule queries.

Edit 

Use this option to update validation rules.

Delete 

Use this option to delete validation rules that are no longer required.

Once a validation rule is added, you can:

2. [Run validation against the reference table](#)

Associating Validation Rules with Reference Tables


After creating a validation rule, you need to associate the validation rule with a reference table.

This allows you to execute the validation rule to validate data in the reference table.

To associate validation rules with reference tables, follow these steps:

1. In the **Workspace** pane, right-click a reference table.

The available options appear.



2. Click **Associate Validations**.

The Associate Validation page appears.

Associating Validation Rules with Reference Tables

Available Validations			Associated Validations		
#	Validation Rule Name	Validation Rule Description	#	Validation Rule Name	Validation Rule Description
1	EMPLOYEE MANAGER CHECK	Rule to check for valid manag			
2	EMPLOYEE NAME RULE	checking for valid employee			
3	INVALID EMP RULE				
4	Incorrect_Object_Id	desc			

- Drag and drop the required validation rule from the **Available Validation** pane to the **Associated Validation** pane.

For more information on adding validation rules, refer to the [Adding Validation Rules](#) topic.

- Click .

The associated validation rules appear on the Associated Validations tab.

Reference Columns				
ID	CREATED BY	CREATED DATE	MODIFIED BY	MODIFIED DATE
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
Records from 1 to 59 of 59				
Additional Table Information				
Table Properties User Defined Fields Associated Validations Associated Codesets Assigned Users				
#	Validation Rule Name		Validation Rule Description	
1	Incorrect_Object_Id		desc	


Running Validations Against Reference Tables

You can run a validation rule query against a reference table after associating the table with the validation rule. Executing validation rule validates the data in the reference table.

To run validation rules against reference tables, follow these steps:

1. In the **Workspaces** pane, click a reference table.

The following page appears. Ensure that you are not in edit mode. If you are in edit mode, click  to cancel edit.




ID	CREATED BY	CREATED DATE	MODIFIED BY	MODIFIED DATE
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143

Records from 1 to 59 of 59

#	Validation Rule Name	Validation Rule Description
1	Incorrect_Object_Id	desc

2. Click .

The Validate Table page appears.



Select Environment: DEV

Select	Validation Name
☒	Incorrect_Object_Id


Running Validations Against Reference Tables

For more information on creating environments, refer to the [Creating Publish Environments](#) topic.

4. Click .

Validation is successfully executed.

The error rows returned by executing the validations are highlighted in red color.



ID	CREATED BY	CREATED DATE	MODIFIED BY	MODIFIED DATE
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
813	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
9	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
9	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
9	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143
9	Administrator	2019-11-01 11:43:51.143	Administrator	2019-11-01 11:43:51.143

Records from 1 to 59 of 59

Additional Table Information

Table Properties User Defined Fields **Associated Validations** Associated Codesets Assigned Users


Associating Codesets With Reference Tables

You can associate codesets with columns of a reference table. Codesets can be used as configurable pick lists so that data can be selected from the drop-down.

To associate codesets with columns of reference tables, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, right-click a reference table.

The available options appear.



3. Click **Associate Codesets**.


The Associate Codeset page appears.

Associating Codesets With Reference Tables

Column Name	Associated Codeset
ID	N/A
NAME	N/A

- Double-click the cell for the required column and select an appropriate codeset.

For more information on codesets, refer to the [Maintaining Enterprise Codesets](#) section.



- Click .

The codeset is associated with the column of the reference table.

The corresponding column in the reference table is now configured as a drop-down and populated with values from the selected codeset.

ID	NAME	CREATED BY	CREATED DATE	MODIFIED BY	MODIFIED DATE
1	ERP	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
2	EDW	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
3	Sales Data Mart	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
4	Admin(1)	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
6	Joe Villers(4)	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
8	Kartik Sridhar(2)	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
10	Resource_Name(3)	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
12	Clear Value	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273
14	Sales Data Mart	Administrator	2019-12-24 15:12:28.273	Administrator	2019-12-24 15:12:28.273

Versioning Reference Tables


You can create versions of reference tables and track the legacy of reference tables. The old version is archived and new version is added to the Reference Table tree in the Workspace pane.

To create versions of the reference tables, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, right-click a reference table.



Ensure that the reference table is not in edit mode (locked condition). If it is in edit mode, click to cancel edit.



Versioning Reference Tables

The New Version page appears.

New Version

Table Name* T_NAME

Version 1.01

Description Reference Table for data integration project.

Version Label

Changed Description*


4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Table Name	Specifies the name of the reference table. For example, Data_Classifications_Levels.
Version	Specifies the new version of the reference table. For example, 1.02.
Description	Specifies the description about the reference table. For example: This reference table serves as domain for the data classification column.
Version Label	Specifies the version label of the reference table. For example, Beta.
Changed Description	Specifies the description of the changes made in the reference table. For example: A new column, Object_ID was added in the reference table.

5. Click .

Table tree.

The previous version of the reference table is archived.




Publishing Reference Tables

You can publish a reference table to a publish environment. Before publishing a reference table, you must ensure that the table has passed all validations successfully.

To publish reference tables, follow these steps:

1. Go to **Application Menu > Data Catalog > Reference Data Manager**.
2. In the **Workspace** pane, right-click a reference table.



3. Click **Publish**.

A warning message appears.

4. Click **Yes**.

The Publish Table page appears.

Publishing Reference Tables

* Publishing the table will create a new version.




Table Name	T_NAME
Version	1.01
Version Label	
Change Description*	
Publish Environment*	DEV Production

5. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.


Field Name	Description
Table Name	Specifies the name of the reference table. For example, Data_Classifications_Levels. It is autopopulated and cannot be edited.
Version	Specifies the current version of the reference table. For example, 1.00. It is autopopulated and cannot be edited.
Version Label	Specifies the version label of the reference table. For example, Beta.
Change Description	Specifies the description about the changes made in the reference table. For example: A new column, Object_ID was added in the reference table.
Publish Environment	Specifies the environment to which the reference table would be published. For example, Production. For more information on creating publish environment, refer to the Creating Publish Environments topic.

The reference table is published. The published version is archived and a new version of the reference table is created in the Workspace pane.



The published version is also saved in the Published Tables pane.

Publishing Reference Tables




Associating Reference Tables with Mappings

Reference data sets the permissible values for other data fields. To standardize your data, you can associate a reference table with mappings. Ensure that you publish the required reference table before associating it with mappings.

To associate reference tables with Mappings, follow these steps:


1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

The Mapping Specification grid appears.



#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEID	int	4	FLOOR
2	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCENAME	varchar	100	REVERSE
3	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEDESC	varchar	150	dbo.RM_Resource

3. Click .
4. Right-click the header menu.



#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length
1	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEID	int	4
2	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCENAME	varchar	100

5. Select the **Reference Table** check box.

The Reference Table column appears in the Mapping Specification grid.

Associating Reference Tables with Mappings

row under the **Reference Table** column.



You can associate multiple source columns with the reference tables.


Mapping Specification						
[Erwin_Map]						
Profiles: Default						
target Column length	Created By	Created Date	CSM Mapping	Last Modified By	Last Modified Date Time	Reference Table
	Administrator	2019-10-21 14:36:15.057	Integrated_Map(1.00)	Administrator	2019-12-10 14:49:07.187	
	Administrator	2019-10-21 14:36:15.057		Administrator	2019-12-10 14:49:07.187	

7. Click .

The reference table is associated with the mappings.

Codeset Manager

To access the Codeset Manager, go to **Application Menu > Data Catalog > Codeset Manager**. The Codeset Manager dashboard appears:



UI Section	Function
1-Workspace	Use this pane to browse through Codesets Workspace and Code Mappings Workspace panes. Codesets Workspace enables you to create and categorize codesets. Code Mappings Workspace enables you to create and categorize code mappings.
2-Right Pane	Use this pane to work on the data based on your selection in the Workspace pane.
3-Published Codesets	Use this pane to browse, view, and export published codesets.
4-Retired Codesets	Use this pane to browse, view, and export retired codesets.

Managing codesets involves the following:

- [Maintaining code mappings](#)

Maintaining Enterprise Codesets

You can create and maintain codesets using the Enterprise section of the Codeset Manager. Under the Enterprise section, you can create codesets, add code name and code value pairs, and version them. You can also publish the codesets to various environments such as development, test, or production and use it to create code crosswalks (mappings).

Maintaining enterprise codeset involves:


- [Creating categories](#)
- [Adding codesets](#)
- [Versioning codesets](#)
- [Deleting codes and codesets](#)
- [Publishing codesets](#)

Creating Categories

Codes are stored in a hierarchical manner Categories > Codesets. You can group codesets into categories based on your organization's projects, departments, or functions. Therefore, before creating codesets, you need to create a category. You can also create sub-categories to group codesets further.

To create categories, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager**.
2. In the **Codesets Workspace** pane, right-click the **Codesets** node.



3. Click **New Category**.

The New Category page appears.

New Category

Category Name*

Category Description

4. Enter the **Category Name** and **Category Description**.

Creating Categories

- **Category Name** - EDW
- **Category Description** - This category contains three codesets, Country Codes, Gender, and Marital Status.

5. Click .

A category is created and saved in the category tree.

Once a category is created, you can:

- [Assign users to the category](#)
- [Add codesets to the category](#)

You can also manage it using the options available on the right-clicking category. [Managing categories](#) involves:

- Updating categories
- Creating sub categories
- Deleting categories
- Creating new codesets
- Exporting codesets
- Deleting codesets
- Exporting category codesets
- Importing codesets
- Assigning users


Managing Categories

Managing categories involves:

- Updating categories
- Creating sub categories
- Deleting categories
- Creating new codesets
- Exporting codesets
- Deleting codesets
- Exporting category codesets
- Importing codesets
- Assigning users

To manage categories, follow these steps:

1. In the **Codesets Workspace** pane, right-click a category.



2. Use the following options:

New Sub Category

Delete Category

Use this option to delete a category that is no longer required. Deleting a category also deletes codesets in it.

New Codesets

Use this option to create new codesets. For more information on creating new codesets, refer to the [Adding Codesets](#) topic.

Export Codesets

Use this option to export codesets to an XLSX file.

Delete Codeset(s)

Use this option to delete one or multiple codesets in a category. On the Delete Codesets page select a codeset(s) and delete them.

Export Category Codesets

Use this option to export the category codesets to an XLSX file.

Import Codesets

Use this option to import codesets from another category. On the Import Codesets page you can browse and upload files.

Assign Users


Use this option to assign users to a category based on your organization's projects, departments, functions, and so on. On the Assign/Unassign Users page, select or remove users and click . For more information on assigning users, refer to [Assigning Users](#) topic.

Assigning Users


You can assign users to a category and enable write access to all sub-folders and codesets within the category.

To assign users, follow these steps:

1. In the **Codesets Workspace** pane, right-click a category.



2. Click **Assign Users**.



3. Use (➡ or ➡➡) to move users from **User ID** box to **Assigned Users** box and use (⬅ or ⬅➡) to move users from **Assigned Users** box to **User ID** box.

Assigning Users

17. Click .

The users are assigned to the category.



Follow the same procedure to add/remove users to/from the category.


Adding Codesets

After creating a category, you can add codesets to enter codes.

Codesets store codes in a code value grid.

To add new codesets, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager**.
2. In the **Codesets Workspace** pane, right-click a category.



3. Click **New Codeset**.

The New Codeset page appears.

The screenshot shows the 'New Codeset' form. It has a title bar with the text 'New Codeset' and standard window controls. The form contains two input fields: 'Codeset Name*' with a red asterisk indicating it is required, and 'Codeset Description'. Both fields are empty text boxes.

Adding Codesets

For example:

- **Codeset Name:** Country Codes
- **Codeset Description:** This codeset has code names and code values for four countries.

5. Click .

A new codeset is created and saved under the Codesets tree.

Once a codeset is created you can add codes to the code value grid in the following ways:

- [Entering codes manually](#)
- [Importing codesets from a MS Excel file](#)
- [Importing codesets through a DB scan](#)


Entering Codes Manually

After creating codesets, you can add codes manually in the code value grid.

To enter codes manually, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager**.
2. In the **Codesets Workspace** pane, click a required.

The Code Value Grid appears.



The screenshot shows the 'Enterprise Codesets' application. On the left is the 'Codesets Workspace' pane with a tree view containing 'Enterprise Codesets', 'Environments', 'Codesets', '3rd Party Flat Files', 'APJ Demo', 'EDW', 'erwin DIS', 'Codesets', 'Sales_Codeset(1.00)', 'ICD 10', 'ICD 9', 'New_Cat', 'New_Category', and 'SAP'. The 'Sales_Codeset(1.00)' item is selected. On the right is the 'Category Details' pane, which contains a 'Code Value Grid'. The grid has five columns: 'Code Name', 'Code Value', 'Code Description', 'Codeset Name', and 'System Name/Environment'. The first row of the grid is highlighted in light gray and contains empty input fields for each column. Above the grid, there are two small icons: a blue and red icon and a gray icon.

Code Name	Code Value	Code Description	Codeset Name	System Name/Environment

3. Click .

4. Click .

The New Code page appears.

Entering Codes Manually

Code Name*

Code Value*

Code Description

System/Environment Name

Please select System/Environment
▼

Start Date

End Date

Activate User Defined Fields ☒ ON

User Defined Field 1

User Defined Field 2

User Defined Field 3

User Defined Field 4

User Defined Field 5

User Defined Field 6

User Defined Field 7

User Defined Field 8

User Defined Field 9

User Defined Field 10

Note* : Date Format = MM/DD/YYYY

5. Enter appropriate values in the fields. Fields marked a with red asterisk are mandatory. Refer to the following table for field descriptions.


Field Name	Description
Code Name	Specifies the code name. For example, Admin.
Code Value	Specifies the code value of the code name. For example, 1.
Code Description	Specifies the description about the code. For example: The code value for Admin is 1.
System/ Environment Name	Specifies the system and environment related with the code. For example, EDW.EDW-DEV. Select the System/Environment name.
Start Date	Specifies the start date of the code validity. For example, 02/24/2020. Enter the start date using

Entering Codes Manually

Field Name	Description
End Date	Specifies the end date of the code validity. For example, 03/22/2021. Enter the end date using  .
Activate User Defined Fields	Switch Activate User Defined Fields to ON to use the user defined fields in the Code Value Grid.
User Defined Field 1-10	You can use your own UI labels for user defined fields. For more information on using UI labels for user defined fields, refer to the Configuring Language Settings topic.

6. Click .

The codes are entered into the Code Value Grid.



The screenshot shows the 'Enterprise Codesets' application. On the left is a tree view under 'Codesets Workspace' containing 'Enterprise Codesets', 'Environments', and 'Codesets'. Under 'Codesets', there are several sub-items including '3rd Party Flat Files', 'APJ Demo', 'Data Integration', 'EDW', 'erwin DIS', 'Codesets', 'Project_System(1.00)', 'Sales_Codeset(1.00)' (which is selected), 'ICD 10', 'ICD 9', 'N_Cat', 'New_Cat', 'New_Category', and 'SAP'. The main area is titled 'Category Details' and contains a 'Code Value Grid'. Above the grid, there are icons for help and a 'Profiles' dropdown set to 'Profile_ABC'. The grid has columns: 'Code Name', 'Code Value', 'Code Description', 'Codeset Name', 'System Name/Environment', 'Active Indicator', 'Delete Indicator', and 'Extended Properties'. It contains four rows of data:

Code Name	Code Value	Code Description	Codeset Name	System Name/Environment	Active Indicator	Delete Indicator	Extended Properties
Admin	1		Sales_Codeset	Project_System	☒	☐	View
Joe Villers	4		Sales_Codeset	Project_System	☒	☐	View
Kartik Sridhar	2		Sales_Codeset	Project_System	☒	☐	View
Resource_Name	3		Sales_Codeset	Project_System	☒	☐	View

7. Use the following options:

Maximize

To maximise the Code Value Grid view, click .

Export to Excel

To download the codeset, click .

[Managing codesets](#) involves:

- Editing Codesets
- Copying Codesets
- Editing Code Value Grid
- Retiring Codesets

Importing Codes using MS Excel Files

You can import codes into Code Value Grid using .xlsx files. The .xlsx file template must be compatible with the Code Value Grid. To ensure the compatibility, download the template and enter the codes and upload it to the Code Value Grid.

To import codes using MS Excel Files, follow these steps:

1. In the **Codesets Workspace** pane, click a codeset.

The Code Value Grid appears.

2. Click  to download the template file.

The template in .xlsx format is downloaded.

3. Enter relevant data in the template.



Set the ACTIVE_FLAG column values to Y, and set the DELETE_FLAG column values to N.


You can use your own UI labels for user defined fields. For more information on using UI labels for user defined fields, refer to the [Configuring Language Settings](#) topic.

The screenshot shows the 'Enterprise Codesets' application. On the left, the 'Codesets Workspace' pane displays a tree view of codesets. The 'Sales_Codeset(1.00)' is selected. On the right, the 'Code Value Grid' pane is visible, showing a table with the following columns: Code Name, Code Value, Code Description, Codeset Name, and System Name/Environment. The table has one row with empty input fields.

4. Click  to enable the edit mode.

5. Click .

Importing Codes using MS Excel Files



6. Browse the updated .xlsx file using **Choose File**.

7. Click .

The codes are uploaded into the Code Value Grid.

Once you upload the codes in the Code Value Grid, you can manage the codesets.

[Managing codesets](#) involves:

- Editing Codesets
- Copying Codesets
- Editing Code Value Grid
- Retiring Codesets


Importing Codes into Code Value Grid using DB Scan

You can import codes into Code Value Grid by scanning a database. Enter connection parameters and establish a connection between the database and erwin DI. Once the connection is established, write an SQL query to preview the required data. You can select the required columns and import them as codes into the Code Value Grid.

To import codes using DB scan, follow these steps:


1. In the **Codesets Workspace** pane, click the required codeset.

The Code Value Grid page appears.



2. Click , to enable edit mode.
3. Click .

The Following page appears.



4. Expand the **Quick Connection** pane.

Quick Connection

*Mandatory Fields

DBType: *

Select DB Type

Driver Name:

IP Address/Host Name:*

Port:*

Database Name:*

System Name:*

TEST

5. Enter appropriate values in the fields (connecting parameters). Fields marked with a red asterisk are mandatory. Refer to the following table for field description.

Importing Codes into Code Value Grid using DB Scan

Field Name	Description
DBType	Specifies the database type. For example, Sql Server. Select the database type from which you wish to scan codes.
Driver Name	Specifies the JDBC driver name for connecting to the database. For example, com.microsoft.sqlserver.jdbc.SQLServerDriver It is autopopulated depending on the DB type. You can also update the driver name.
IP Address/Host Name	Specifies the IP address or server host name of the database. For example, localhost.
Port	Specifies the port to connect with the database. For example: 1433 is the default port for a Sql Server database type.
Database Name	Specifies the database name being used to connect to the codeset. For example, ErwinDIS931.
System Name	Specifies the name of the system related with the codeset. For example, EDW. The name of the system should be same as provided in Metadata Manager.
System Environment Name	Specifies the name of the environment related with the codeset. For example, EDW-DEV. The name of the environment should be same as provided in Metadata Manager.
User Name	Specifies the user name to connect with database. For example, sa.
Password	Specifies the password to connect with database. For example, goerwin@1.

Importing Codes into Code Value Grid using DB Scan

Field Name	Description
URL	Specifies the full JDBC URL that is used to establish a connection with the database. For example, <code>jdbc:sqlserver://SERVER_NAME:PORT#;databaseName=DatabaseName</code> It is autopopulated based on the other parameters.

- Click  to test the connection.

On a successful connection, Connection Successful pop-up appears.

- Write an SQL query in the **Query Panel** to fetch the required data from the database.

- Click  to validate the query.

- Click  to preview the data.

- Double-click the **Select CSMHeader Template** cell of the required column.

The columns of the Code Value Grid appears as an option list.

Importing Codes into Code Value Grid using DB Scan

The screenshot shows a software interface with three main panels:

- Query Panel:** Contains the query text: `Select*from CAT_DIALOG_TAB`.
- Quick Connection:** Contains database connection details:
 - DBType: * Sql Server
 - Driver Name: com.microsoft.sqlserver.jdbc.S
 - IP Address/Host Name: * localhost
 - Port: * 1433
 - Database Name: * ErwinDIS931
 - System Name: * A_System
- Query Result:** Displays a table with the following data:

#	CAT_DIALOG_TAB_ID	CAT_DIALOG_PROFILE_ID	CAT_DIALOG_TAB_NAME	CAT_DIALOG_TAB_PROPERTIES	CREATED_BY
		Select CSMHeader Template	Code Value	Select CSMHeader Template	Select CSMHeader Template
1	1	Code Name	DefaultTab		Administrator
2	2	Code Value	DefaultTab		Administrator
3	3	Code Description	DefaultTab		Administrator
4	4	System Environment Name	DefaultTab		Administrator
5	5	Start Date	DefaultTab		Administrator
		End Date	DefaultTab		Administrator

Note: Only top 50 rows will be displayed in grid.

11. Select the required Code Value Grid column.



You can select multiple columns from the database.

12. Click  to import the selected columns into the **Code Value Grid**.

The selected columns are imported in the **Code Value Grid**.

Once you import the codes in the Code Value Grid, you can manage codesets.

Managing codesets involves:

- Editing Codesets
- Copying Codesets
- Editing Code Value Grid
- Retiring Codesets

Managing Codesets


Managing Codesets involves the following:

- Editing codesets
- Deleting codesets
- Creating new codeset version
- Publishing codesets
- Copying codesets
- Retiring codesets

You can manage the codesets and update its details.

To manage codesets, follow these steps:

1. In the **Codesets Workspace** pane, expand a category.
2. Expand the **Codesets** node, and right-click a codeset.



3. Use the following options:

Edit Codeset

Use this option to update codeset's details.

Delete Codeset

Use this option to delete a codeset.

New Version

Use this option to create a new codeset version. For more information on creating new codeset version, refer to [Versioning Codesets](#) topic.

Managing Codesets

Use this option to publish the codesets. For more information on publishing codesets, refer to [Publishing Codesets](#) topic.

Copy

Use this option to copy the selecte codeset and paste it in different category.

Retire

Use this option to retire a codeset and it is moved to Retired Codesets pane. After you retire a codeset, you cannot retrieve that codeset.


Versioning Codesets

You can version codesets and maintain the legacy of codesets with a record of changed description.

To create new versions of codesets, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager**.
2. In the **Codesets Workspace** pane, right-click a codeset.

 Ensure the codeset is in edit mode. Click  to cancel edit mode.



#	Category Name
1	SAP
2	EDW
3	EDW
4	EDW
5	ICD 10
6	ICD 10
7	ICD 10
8	ICD 10
9	ICD 10
10	ICD 9

3. Click **New Version**.

The New Codeset Version page appears.

Versioning Codesets

Codeset Name

Codeset Version

Codeset Description

desc

Codeset Version Label

Codeset Changed Description *

Metadata management

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field description.

Field Name	Description
Codeset Name	Specifies the name of the codeset whose version is being created. For example, Country Codes. It is autopopulated with the codeset name and cannot be edited.
Codeset Version	Specifies the new version of the codeset. For example, 1.03.
Codeset Description	Specifies the description about the codeset. For example: This codeset has code names and code values for four countries. It is autopopulated with the codeset description and cannot be edited.
Codeset Version Label	Specifies the version label of the codeset. For example, Beta.
Codeset Changed Description	Specifies the description about the changes in the codeset. For example: Code Value for CANADA was changed to CAN.

5. Click

Deleting Codes and Codesets

You can logically delete and restore the codes, and also permanently delete the codesets.

To delete codesets, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager**.
2. In the **Codesets Workspace** pane, expand a category.
3. Expand a **Codesets** node and click a codeset.

The Code Value Grid appears

Enterprise Codesets		Codeset Mappings						
Codesets Workspace		Category Details						
Code Value Grid		Profiles : Profile_ABC						
Code Name	Code Value	Code Description	Codeset Name	System Name/Environment	Active Indicator	Delete Indicator	Extended Properties	
Admin	1		Sales_Codeset	Project_System	☒	☐	View	
Joe Villers	4		Sales_Codeset	Project_System	☒	☐	View	
Kartik Sridhar	2		Sales_Codeset	Project_System	☒	☐	View	
Resource_Name	3		Sales_Codeset	Project_System	☒	☐	View	

4. Select **Delete Indicator** check box for relevant Codeset Name from the Codeset Value Grid.

A warning message appears.

5. Click **Yes**.

The code is logically deleted and can be restored or purged.

To restore or purge logically deleted codes, follow these steps:

1. Click .

The Logically Deleted Codes page appears.


Deleting Codes and Codesets

Select Rows	Code Name	Code Value	Code Description	Codeset Name	System Name/Environment	Active Indicator	Start Date	End Date
☐	Admin	1		Sales_Codeset	Project_System	☒		
☐	Joe Villers	4		Sales_Codeset	Project_System	☒		
☐	Kartik Sridhar	2		Sales_Codeset	Project_System	☒		

2. Select required rows.
3. Click , to delete the selected rows.
4. Click , to restore the selected rows.

To permanently delete codesets, follow these steps:

1. Right-click a codeset.



To delete a codeset, ensure the codeset is in edit mode. Click  to cancel edit mode.

2. Click **Delete Codesets**.

A warning message appears.

Deleting Codes and Codesets


The codeset is deleted.

Publishing Codesets

You can publish your codesets to an environment. To publish the codesets, ensure that you have created and setup an environment.


To create publish environments, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager**.
2. In the **Codesets Workspace** pane, right-click the **Environments** node.



3. Click **New Environment**.

The New Environment page appears.




4. Enter **Environment Name**.
5. Click .

A new publish environment is created and saved in the Publish Environments pane.

To

1. Go to **Application Menu > Data Catalog > Codeset Manager>**.
2. In the **Codesets Workspace** pane, right-click a codeset.



3. Click **Publish**.

The Publish Codesets page appears.

Publishing Codesets

* Publishing the Codeset will create a new version.

Codeset Name

Codeset Version

Codeset Version Label

Codeset Changed Description*

Publish Environment*

DEV

PROD

Production

Test


4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field description.

Field Name	Description
Codeset Name	Specifies the name of the codeset which is being published. For example, Country Codes. It autopopulates with the codeset name and cannot be edited.
Codeset Version	Specifies the new version of the codeset. For example, 1.03. It autopopulates with the new version and cannot be edited.
Codeset Version Label	Specifies the version label of the codeset. For example, Beta.
Codeset Changed Description	Specifies the description about the changes in the codeset. For example: Code Value for CANADA was changed to

Publishing Codesets	
Field Name	Description
	CAN.
Publish Environment	Specifies the publish environment to which the codeset is being published. For example, Production.

5. Click .

The codeset is published successfully and the published codesets move under Published Codesets pane.



Once the source and target codesets are published, you can [create code mappings](#).



You can create code mappings without publishing source or target codesets, but it is recommended that you create code mappings after publishing the codesets.

Maintaining Code Mappings

The Codeset Mappings section in Codeset Manager allows you to define and categorize code mappings. The process is standardized with ability to version and publish code mappings to various environments. Further, these published code mappings can be associated with data item mappings in the Mapping Manager.

Maintaining Code Mapping involves:


- [Creating Categories](#)
- [Creating code maps](#)
- [Versioning codemaps](#)
- [Publishing and association codemaps](#)

Creating Categories

Code maps are stored in a hierarchical manner Categories > Mappings. You can also create sub-categories under a category to provide one more level of categorization to mappings.

To create a category, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager > Codeset Mappings**.
2. In the **Code Mappings Workspace** pane, right-click the **Code Mappings** node.



3. Click **New Category**.

The New Category page appears.

 A screenshot of the 'New Category' dialog box. The dialog has a title bar with 'New Category' and standard window controls. Inside, there are two input fields: 'Category Name *:' with a red asterisk indicating it is required, and 'Category Desc:'. There are also icons for saving and closing the dialog.

4. Enter **Category Name** and **Category Description**.

For example:

Creating Categories


Category Description: This category contains two code mappings, Gender Crosswalk and Marital Status Crosswalk.

5. Click .

A new category is created and saved under the category tree.

To create sub-categories under a category, follow these steps:


1. Under the **Code Mappings Workspace** pane, right-click the required category.



2. Click **New Sub Category**.

The New Category page appears.

Creating Categories



Category Name * :

Category Desc :

3. Enter **Category Name** and **Category Description**.

For example:

- **Category Name:** EDW-Finance
- **Category Description:** This sub-category contains two code mappings, Gender Crosswalk and Marital Status Crosswalk.

4. Click .

A new sub-category is created and saved under the sub-category tree.

Once a category is created, you can:

- [Creating code crosswalks for mappings](#)
- [Versioning code maps](#)
- [Associating code maps with data item mappings](#)

You can also manage it using the options available on the right-clicking category. [Managing categories](#) involves:

- Updating categories
- Deleting categories
- Importing legacy maps
- Assigning users

Managing Categories


Managing categories involves:

- Updating categories
- Deleting categories
- Importing legacy maps
- Assigning users

To manage categories, follow these steps:

1. In the **Codesets Mappings** pane, click a category.


The Category Mapping Grid appears.



The screenshot shows the 'Codeset Manager' window with the 'Codeset Mappings' tab selected. On the left, the 'Code Mappings Workspace' tree shows a hierarchy: 'Code Mappings' > 'TechPubs' > 'Mappings' > 'map1 (1.00)' > 'Sub techPubs'. The 'map1' category is selected. The 'Codeset Mapping Grid' on the right displays a table with the following data:

#	Map Name	Lock Status	Locked By	Description	Created
1	map1	☐			Administ

2. Right-click a category.



The screenshot shows the same 'Codeset Manager' window, but with a right-click context menu open over the 'map1' category in the 'Code Mappings Workspace' tree. The menu options are:

- New Sub Category
- Edit Category
- Delete Category
- New Map
- Import Legacy Maps
- Assign Users

The 'Codeset Mapping Grid' remains visible in the background.

3. Use the following options:

Edit Category

Delete Category

Use this option to delete a category. Deleting a category also deletes the maps in it.

Import Legacy Maps

Use this option to import old maps to the catalog.

Assign Users

Use this option to assign users to a category based on your organization's projects, departments, functions, and so on.

Creating Code Crosswalks (Mappings)

You can create code crosswalks (mappings) for the source and target codesets in the Code-set Manager. These codesets can have the same or different code values. Using the Auto-Map functionality, you can map source and target codesets with:


- Same code values
- Different code values

Creating Code Crosswalks - Source and Target Codesets with Same Code Value

You can use Auto-Map functionality to map source and target codesets having same code values.

To create code mappings when source and target codesets have same code values, follow these steps:

1. Right-click the required category.



2. Click **New Map**.

Creating Code Crosswalks (Mappings)

New Codeset Map

Codeset Map Name*

Codeset Map Version

Codeset Map Description

Source Codeset

- 3rd Party Flat Files.Misc Marital Status Codes
- 3rd Party Flat Files.Misc Gender Codes
- APJ Demo.Gender Codes
- EDW.Gender
- EDW.Marital Status
- EDW.Country Codes

Source

- 3rd Party Flat Files
- 3rd Party Flat Files.3rd Party Flat Files
- A_System
- A_System.A_Environment
- AdventureWorks
- AdventureWorks.AdentureWorks_Staging

Target Codeset

- 3rd Party Flat Files.Misc Marital Status Codes
- 3rd Party Flat Files.Misc Gender Codes
- APJ Demo.Gender Codes
- EDW.Gender
- EDW.Marital Status
- EDW.Country Codes

Target

- 3rd Party Flat Files
- 3rd Party Flat Files.3rd Party Flat Files
- A_System
- A_System.A_Environment
- AdventureWorks
- AdventureWorks.AdentureWorks_Staging

Auto Map ☐ *Auto mapping occurs for source and target codes having the same values.

3. Enter the **Codeset Map Name** and **Codeset Map Description**.

For example:

- **Codeset Map Name:** Gender Crosswalk
- **Codeset Map Description:** The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.

4. Select the **Source Codeset/System** and **Target Codeset/System**.

5. Select the Auto Map check box and click .

A new code mapping is created and source and target codesets are mapped in the Codeset Mapping Grid.

Enterprise Codesets

Codeset Mappings

Code Mappings Workspace

Code Mappings

APJ Demo

C_Name

EDW

ICD Crosswalks

Integrated_Data

Mappings

Integrated_Map(1.00)

Map1(1.00)

New_Category

Codeset Mapping Grid

#	Source Category	Source Codeset	Source Codeset Version	Source System/Environment	Source Code Description	Source Code ID
1	erwin DIS	Sales_Codeset	1.00	Project_System		710
2	erwin DIS	Sales_Codeset	1.00	Project_System		711
3	erwin DIS	Sales_Codeset	1.00	Project_System		712
4	erwin DIS	Sales_Codeset	1.00	Project_System		713

Records from 1 to 4

25 rows per page

CSM MapSpec Overview

Codeset Map Name

Integrated_Map

Codeset Map Version

1.00

Codeset Tree

Codesets

3rd Party Flat Files

APJ Demo

Data_Integration

Codesets

Integrated_Codeset

11

22

33

44

EDW

erwin DIS

Codesets

Project_System

Sales_Codeset

1

2

3

4

ICD 10

ICD 9

N_Cat

New_Cat

New_Category

SAP

6. Click  to validate the code mapping.

Creating Code Crosswalks - Source and Target Codesets with Different Code Value

Codesets having different code values can be mapped using the drag and drop method.

To create code mappings when source codesets and target codesets have different code values, follow these steps:

Creating Code Crosswalks (Mappings)

Enterprise Codesets

Codeset Mappings

Code Mappings Workspace

Code Mappings

APJ DEMO

C_Name

EDW

ICD Crosswalks

Integrated_Data

Mappings

New_Category

New Sub Category

Edit Category

Delete Category

New Map

Import Legacy Maps

Assign Users

Codeset Mapping Grid

#	Source Category	Source Codeset	Source Codeset Version
	in DIS	Sales_Codeset	1.00
	in DIS	Sales_Codeset	1.00
	in DIS	Sales_Codeset	1.00
	in DIS	Sales_Codeset	1.00

- Click **New Map**.

The New Codeset Map page appears.

Creating Code Crosswalks (Mappings)

Codeset Map Name*

Codeset Map Version

1.00

Codeset Map Description

Source Codeset

3rd Party Flat Files.Misc Marital Status Codes

3rd Party Flat Files.Misc Gender Codes

APJ Demo.Gender Codes

EDW.Gender

EDW.Marital Status

EDW.Country Codes

Source

3rd Party Flat Files

3rd Party Flat Files.3rd Party Flat Files

A_System

A_System.A_Environment

AdventureWorks

AdventureWorks.AdentureWorks_Staging

Target Codeset

3rd Party Flat Files.Misc Marital Status Codes

3rd Party Flat Files.Misc Gender Codes

APJ Demo.Gender Codes

EDW.Gender

EDW.Marital Status

EDW.Country Codes

Target

3rd Party Flat Files

3rd Party Flat Files.3rd Party Flat Files

A_System

A_System.A_Environment

AdventureWorks

AdventureWorks.AdentureWorks_Staging

Auto Map ☐

*Auto mapping occurs for source and target codes having the same values.

3. Enter the **Codeset Map Name** and **Codeset Map Description**.

For example:

- **Codeset Map Name:** Gender Crosswalk
- **Codeset Map Description:** The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.

4. Select the Source Codeset/System.

5. Click .

The source codesets details are updated in the Codeset Mapping Grid.

Creating Code Crosswalks (Mappings)


The screenshot displays the 'Enterprise CodeSets Codeset Mappings' application. The main window is divided into three panes:

- Code Mappings Workspace (Left):** A tree view showing the project structure, including 'Code Mappings', 'APJ Demo', 'C_Name', 'EDW', 'ICD Crosswalks', 'Integrated_Data', 'Mappings', 'Integrated_Map(1.00)', and 'New_Category'.
- Codeset Mapping Grid (Center):** A table with the following columns: #, Source Category, Source Codeset, Source Codeset Version, Source System/Environment, Source Code Description, and Source Code ID. It contains four rows of mappings for 'erwin DIS' source category, all pointing to 'Sales_Codeset' version '1.00' in the 'Project_System' environment.

#	Source Category	Source Codeset	Source Codeset Version	Source System/Environment	Source Code Description	Source Code ID
1	erwin DIS	Sales_Codeset	1.00	Project_System		710
2	erwin DIS	Sales_Codeset	1.00	Project_System		711
3	erwin DIS	Sales_Codeset	1.00	Project_System		712
4	erwin DIS	Sales_Codeset	1.00	Project_System		713
- Codeset Tree (Right):** A tree view showing the hierarchy of code sets, including 'CodeSets', '3rd Party Flat Files', 'APJ Demo', 'Data_Integration', 'Codesets', 'Integrated_Codeset', 'EDW', 'erwin DIS', 'Codesets', 'Project_System', 'Sales_Codeset', 'ICD 10', 'ICD 9', 'N_Cat', 'New_Cat', 'New_Category', and 'SAP'.

Below the grid is the 'CSM MapSpec Overview' section, which includes fields for 'Codeset Map Name' (Integrated_Map) and 'Codeset Map Version' (1.00).

6. Click .
7. Scroll to right of the Codeset Mapping Grid to see the Target Code Value column.
8. In **Codeset Tree**, expand the target category and the Codesets node.
9. Drag and drop the target codeset into the Code Set Mapping Grid under the Target Code Value column.



10. Click .

The code mappings are successfully saved.

11. Click  to validate the code mapping.

The code map is validated. Ensure that all the required codes are mapped.

Use the following options:

Export

To download the code map details in .xlsx format, click .

Extend Mapping Grid

To extend the Codeset Mapping Grid, click .

Once the code map is created, you can:

- [Edit Code Mappings](#)
- [Create new version of the code map](#)
- [Publish and associate the code map with data item mappings](#)

Editing Code Mappings

You can update source codesets and target codesets in the Codeset Mapping Grid.

To update source codesets, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager > Codeset Mappings**.
2. In the **Code Mappings Workspace** pane, expand a category and click a codemap.

The Codeset Mapping Grid and CSMMMapSpec Overview pane appears.

The screenshot displays the 'Codeset Mappings' interface. On the left is the 'Code Mappings Workspace' pane with a tree view showing categories like 'APJ Demo', 'C_Name', 'EDW', 'ICD Crosswalks', 'Integrated_Data', 'Mappings', and 'New_Category'. The 'Mappings' category is expanded, showing 'Integrated_Map(1.00)' and 'Map1(1.00)'. The main area is divided into two panes. The top pane is the 'Codeset Mapping Grid', which contains a table with 4 rows of data. The bottom pane is the 'CSMMMapSpec Overview', which contains input fields for 'Codeset Map Name' (set to 'Integrated_Map'), 'Codeset Map Version' (set to '1.00'), and 'Codeset Map Description' (set to 'Code map when source and target have different code values.').

#	Source Category	Source Codeset	Source Codeset Version	Source System/Environment	Source Code Description	Source Code ID
1	erwin DIS	Sales_Codeset	1.00	Project_System		710
2	erwin DIS	Sales_Codeset	1.00	Project_System		711
3	erwin DIS	Sales_Codeset	1.00	Project_System		712
4	erwin DIS	Sales_Codeset	1.00	Project_System		713

Records from 1 to 4 | 25 rows per page

CSMMMapSpec Overview

Codeset Map Name: Integrated_Map

Codeset Map Version: 1.00

Codeset Map Description: Code map when source and target have different code values.

3. In **CSM Mapping Overview** pane, click .

You can update Codeset Map Name and Codeset Map Description.




You cannot edit Codeset Map Version.

4. Select a new Source Codeset and Source System/Environment.
5. Select a Target Codeset and Target System/Environment.
6. Click .

Editing Code Mappings

doesn't update in the Codeset Mapping Grid. You need to drag and drop target codeset from the Codeset Tree to Codeset Mapping Grid.



To update target codeset in the Codeset Mapping Grid, follow these steps:

1. In the Codeset Mapping Grid, click .



The Codeset is locked and other users cannot make changes.

2. In the Codeset Tree, expand the target category and the **Codesets** node.
3. Drag and drop the target codeset into the Code Set Mapping Grid under the Target Code Value column.
4. Click .


The target codeset is updated in the Codeset Mapping Grid.

To update target code values in the Codeset Mapping Grid, follow these steps:

Editing Code Mappings

1. In the Codeset Mapping Grid, click .

2. Double-click a cell under the Target Code Value column and update it with the one of the options available.



The screenshot shows the 'Codeset Manager' window with the 'Codeset Mappings' tab selected. The 'Codeset Mapping Grid' displays a table of mappings. The 'Target Code Value' column for the 'Admin' row is being edited, showing a dropdown list with options: '11 (Integrated_Cod', '44 (Integrated_Cod', '22 (Integrated_Cod', '33 (Integrated_Cod', and 'Clear Target'. The 'CSM MapSpec Overview' section below the grid shows the 'Integrated_Map' codeset map with version '1.00' and a description: 'Code map when source and target have different code values.'

Source Code Name	Source Code Value	Target Code Value	Target Code Name	Target Code ID	Target Code Descrip	Target System/Environment	Target
Admin	1	11	Admin	714		Project_System	Integr
Joe Villers	4	11 (Integrated_Cod	Karlik Sridhar	716		Project_System	Integr
Karlik Sridhar	2	22 (Integrated_Cod	Resource_Name	717		Project_System	Integr
Resource_Name	3	33 (Integrated_Cod	Joe Villers	715		Project_System	Integr

CSM MapSpec Overview

Codeset Map Name: Integrated_Map

Codeset Map Version: 1.00

Codeset Map Description: Code map when source and target have different code values.

3. Click .

The target code values are updated.


Versioning Code Mappings

You can create versions of code mappings and track legacy of a code map.

The new version is available in the Code Mappings Workspace under the Mappings tree.

To create new versions of code mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager > Codeset Mappings**.
2. In the **Code Mappings Workspace** pane, right-click a codeset map.



3. Click **New Version**.
4. The New Codeset Map Version page appears.

Versioning Code Mappings

Codeset Map Name*

New_Codeset_Map

Codeset Map Version

1.02

Codeset Map Description

Map Version Label

Map Changed Description*

5. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Codeset Map Name	Specifies the name of the codeset map. For example, Gender Crosswalk.
Codeset Map Version	Specifies the new version of the codeset map. For example, 1.02.
Codeset Map Description	Specifies the description about the codeset map. For example: The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.
Map Version Label	Specifies the version label of the codeset map. For example, Beta.

6. Click

The new version is created and saved in the Mappings tree while the older version is archived.

Associating Code Maps with Data Item Mappings

A code map can be associated with a data item mapping to standardize data across the organization. These code maps are maintained in Codesets Manager. For more information on codesets and code mappings, refer to the [Codeset Manager](#) section.


Before associating a code map with data item mappings, ensure that you publish the code map.

Publishing Code Maps

To publish code maps, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager > Codeset Mappings**.
2. In the **Code Mappings Workspace** pane, right-click a code map.


The available options appear.



3. Click **Publish**.

The Publish Codeset Map page appears.

Associating Code Maps with Data Item Mappings



Codeset Map Name* Integrated_Map

Codeset Map Version 1.01

Codeset Map Description Code map when source and target have different code values.

Map Version Label

Map Changed Description* Updated Code Values.

Publish Environment* DEV
PROD
Production
Test

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Codeset Map Name	Specifies the name of the code map. For example, Gender Crosswalk.
Codeset Map Version	Specifies the new version of the code map. For example, 1.02.
Codeset Map Description	Specifies the description about the code map. For example: The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.
Map Version Label	Specifies the version label of the code map. For example, Beta.
Map Changed Description	Specifies the description about the changes made in the code map. For example: Code values were updated.
Publish Environment	Specifies the environment where the code map is being published.


Associating Code Maps with Data Item Mappings

Field Name	Description
	For example, test. You can create publish environments in Enterprise Codesets. For more information on creating publish environments, refer to the Publishing Codesets topic.

5. Click .

The code map is published and it can be found in the Published Code Mappings pane under the selected Publish Environment.

A new version of the code map is created under the Mappings tree.



A published code map can be associated with a mapping in the Mapping Manager. The published code map is available under the Code Mappings Catalog.

Associating Code Maps

To associate published code maps with data item mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required map.

Associating Code Maps with Data Item Mappings

Workspace Mappings

- Project (4)
 - Transformations
 - Test Cases
 - Mappings
 - Data Integration (v1.00)**
 - MappingTargets
 - DragDrop (v1.00)
 - SalesforceIntegration (v1.00)
 - TechPubs (v1.00)
- project 1 (4)
- Project Tech Pubs (8)
- Tech Pubs Online (6)
- TechPubs (6)

Mapping Specification

Graphical Designer

Test Specification

Workflow Log

Profiles: [Data Integration]

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle	nvarchar	30
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60

3. Click .

4. In the **Mapping Specification** grid, right-click the header menu.

Test Specification

Workflow Log

Profiles: Mapping_Designer_Profile

Target Table	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag
customers	PostalCode	nvarchar	10	0		
customers	City	nvarchar	15	0	0	☒

Target Table Alias
☐ Target Column Class
☐ Target Column Alias
☐ Target Business Key Flag
☒ CSM Mapping
☐ Specification Artifacts
☐ Reference Table
☐ Business Rule

Metadata Catalog

Metadata Combo C

Metadata

Systems

Search

erwin DI Suite

erwin DM

5. Select the **CSM Mapping** check box.

The CSM Mapping Column appears in the Mapping Specification grid.

6. In the right pane, expand **Code Mapping Catalog**.

7. Drag the code map into the **Mapping Specification** grid and drop it under the **CSM Mapping** column for the required row.

or click .

The code map is associated with the data item mappings.